


## Annexure 1 – DR Connection parameters of BOLT Plus Trading system for Currency Derivatives segment

Trading members can connect to the DR site of BOLT Plus trading system using either BOLT TWS or 3<sup>rd</sup> party trading application of empanelled vendors or in-house developed systems through IML exe ver.7.0 & above or ETI APIs as follows –

### 1. BOLT TWS Users

Trading members shall have to change the technical connection parameters in the configuration settings window at the time of login. Configuration settings window can be invoked using the scrip profile icon or “Shift+F12” shortcut keys on BOLT TWS.



Segment	Production IP	Port	Disaster Recovery IP	Port
Equity 1	10 . 255 . 255 . 6	12908	10 . 255 . 241 . 10	12908
Equity 2	10 . 255 . 255 . 7	12908	10 . 255 . 241 . 11	12908
Bolt	10 . 1 . 101 . 45	2449	10 . 1 . 101 . 142	2449
MCast IP 1	227 . 0 . 0 . 21	12996	Mcast IP/Port Same as Production	
MCast IP 2	228 . 0 . 0 . 1	1111		
Derivative 1	10 . 255 . 255 . 13	11908	10 . 255 . 241 . 11	11908
Derivative 2	10 . 255 . 255 . 12	11908	10 . 255 . 241 . 10	11908
MCast IP	228 . 0 . 0 . 21	11996	Mcast IP/Port Same as Production	
Currency 1	10 . 255 . 255 . 12	10908	10 . 255 . 241 . 10	10908
Currency 2	10 . 255 . 255 . 13	10908	10 . 255 . 241 . 11	10908
MCastIP	229 . 0 . 0 . 21	10996	Mcast IP/Port Same as Production	

**General Settings**  
 Term ID: MBOCKNXXMMGB IML Port: 6001  
 Interface: . . . ☐ Broadcast Logging

**Master Download Settings**  
 Primary DLOAD IP: 190 . 9 . 200 . 200 Secondary DLOAD IP: 0 . 0 . 0 . 0


**Other Settings (Immediately Apply)**  
 Market Report Frequency: 24 x 10 Sec Location ID: 1234567890123465  
 Market Information Update Frequency: Medium

**Scrip Id / Name Display**  
 Equity: ☒ Scrip Id ☐ Scrip Name  
 Derivative: ☐ Scrip Id ☒ Scrip Name  
 Currency: ☐ Scrip Id ☒ Scrip Name

Buttons: Change Save Cancel

## 2. 3<sup>rd</sup> party trading application through IML or ETI APIs

- i. Connecting through IML exe – members shall have to change the technical connection parameters in the IML configuration settings window at the time of login.



**Configuration Setting**

Connection Preference  
☒ BOLTplus ☐ BOLTplus and BOLT

Member Settings  
 Member Id: 1 Trader Id: 1

BOLTplus Host Side (Interactive and Broadcast )  
 Host IP: 10.255.255.12 Port No: 10908  
 Alt Host IP: 10.255.255.13 Alt Port No: 10908  
 DR Host IP: 10.255.241.10 DR Port No: 10908  
 DR Alt Host IP: 10.255.241.11 DR Alt Port No: 10908  
 Host MulticastIP 1: 229.0.0.21 UDP Host Port 1: 10996  
 Host MultiCast IP 2: UDP Host Port 2:

BOLT Host Side (Interactive)  
 Host IP: 10.1.101.93 Port No: 2349  
 Alt Host IP: 10.1.101.94 Alt Port No: 2349

TPS Side / Current Settings  
 TPS Port No: 6001 Interface IP: 10.228.61.13  
 UDP Address 1: 0 UDP Port 1: 0  
 UDP Address 2: 0 UDP Port 2: 0

Change Save Cancel Close

- ii. Connecting through ETI – members shall have to change the technical connection parameters in their respective trading application as follows –

Primary DR – IP: 10.255.241.10; Port: 10908

Secondary DR – IP: 10.255.241.11; Port: 10908

\*\*\*\*End of Document\*\*\*\*