

- A. The DR settings are available in the Auto Download of Masters.zip file. You can download the same. Additionally, you can also download the Bolt+ DR Settings.zip folder and copy and replace the files in the Bolt+ folder.
- B. On the DR day, after initialising the Application Exe, please go to the Connection Settings tab.

Login

Login Connection Settings Forgot Passwod Multicast

BOLT+ **BSE**
EXPERIENCE THE NEW

User Id: TEST
 Password:
 Transaction Password:

Powered by MarketPlace Technologies Pvt.Ltd. @Copyrights 2013
Note : - Best viewed in 1024x768 resolution

☒ Retain Last Login Info. **Login** **Exit**

Downloads
☐ Client Master
☐ Script Master

Contact Us : +91 22 2272 8080

- C. In the Connection Settings Tab, please select the **DR Option** and Click on **SAVE**.

Login

Login **Connection Settings** Forgot Passwod Multicast

Select connection Type DR **Edit** **Cancel**

Main Server Settings
 IP Address: 10.1.101.193
 Proxy Server Settings
 IP Address: Port: User: Password:

Interactive Settings
 IP Address: 10.1.101.193:9091

Broadcast Settings
☐ Broadcast Over HTTP
 Connection Type: ☐ VSAT ☒ Dial Up ☐ Local LAN For Local LAN: ☐ UDP ☒ Multicast
 Server IP Address: 10.1.101.193:9092 Receive IP Address:

FTP Settings
 FTP Server: 10.1.101.193 Username: bseftp Pwd: *****

Compression
 Socket Compression: No Compression ☐ Use HTTP Compression

☐ Combined MBP LockTime (min): 480 LogOutTime (min): 700
☐ Use Secure HTTP HTTP TimeOut (sec): 999

Contact Us : +91 22 2272 8080 **Save**

- D. After Clicking on Save, please click on the LOGIN tab and enter the login credentials and proceed with Login .

Please note that the above settings need to be changed by users who Log in from the BSE private Network (Lease Lines/VSAT).

Internet Users are not needed to change any settings.